Item Item

Item

Use this basic rule to move or copy text from the character screen to the title bar or status bar.

This chapter covers the following topics:

- Maintaining the Item Rules
- Overview of Options


Maintaining the Item Rules

You have to specify the region which contains the desired text. Text can be moved or copied to the status bar, the window title or the dialog title. It is also possible that specific regions are not shown at all.

To display all defined Item rules

• From the **Basic** menu, choose **Item**.

The Item dialog box appears. When the Item dialog box is shown, a check mark is shown next to the **Item** command.



When items have already been defined, the defined regions are shown in this dialog box. The scope window then shows the outlines of all defined items.

The color red in the symbol to the left of each defined region indicates that this rule has been disabled. A symbol with the color green indicates that the rule is enabled.

The following command buttons are available:

New	Add a new Item rule (see below).
Edit	Modify the selected Item rule. Alternative: double-click an Item rule.
Delete	Delete the selected Item rule. Alternative: choose Delete from the Edit menu or press DEL to delete the selected Item rule.

To add an Item rule


- 1. Make sure that the resource file that is to be used as a template is shown in the scope window.
- 2. Display the Item dialog box as described above.
- 3. Choose the **New** button.
- 4. In the scope window, use the mouse to select the region in which this rule is to be applied.

The Item Configuration dialog box appears.

- 5. Specify all required information as described below.
- 6. Choose the **OK** button.

Overview of Options Item

Overview of Options



Disable this Item

When this check box is selected, this Item rule is disabled.

Row / Column / Width

The position of the selected region. Using the spin buttons, you can manually adjust the values.

Description

The text found in the selected region is automatically provided as a description. This helps to identify the different Item rules.

Item Overview of Options

Location

Select one of the following option buttons to specify where the text found in the defined region is to be shown:

• Status bar

The text is shown at the left, center or right of the status bar, depending on the option button selected in the Alignment group box.

Window title

The text is shown in the title bar of the viewer window (instead of "Entire Screen Builder" which is shown by default).

• Dialog title

The text is shown in the title bar of the viewer window. When a window title has also been defined, it is shown behind the window title.

Non Display

The text is not shown at all.

Alignment

Only available when the option button **Status bar** is selected. Select one of the option buttons in this group box to specify whether the text is to be shown at the left, center or right of the status bar.

Apply this item

Select one of the option buttons in this group box to define where this rule is to be applied:

- only in parent windows,
- only in child windows, or
- in both parent and child windows.

Copy/Move

Select one of the option buttons in this group box to specify whether the text in the defined region is to be copied or moved. When the text is moved, it is no longer shown in its original position.